[FAQ08177][BMT][internel use]电池高温关机温 度客制化

[DESCRIPTION]

电池高温关机温度默认是60度,如果要修改,应该修改哪些点 [SOLUTION]

Notice: 电池高温关机温度请不要随意克制化,请根据自己的需求适当克制化,克制化的温度请在电池允许的范围内,如果过高,会有电池爆炸的危险!!

1) JB以前的版本: alps/frameworks/base/services/java/com/android/server/batteryservice.java

private final void ShutdownlfOverTemp() {
 // shut down gracefully if temperature is too high (> 68.0C)
 // wait until the system has beoted before attempting to display the shutdown dialog.
 if (mBatteryTemperature (> 680 && ActivityManagerNative.isSystemReady()) {
 Intent intent = new intent(Intent.ACTION_REQUEST_SHUTDOWN);
 intent.putBxtra(Intent.EXTRA_KEY_CONFIRM, false);
 intent.setFlags(Intent.FLAG_ACTIVITY_NEW_TASK);
 mContext.startActivity(intent)(inten

3. Android 层 68 度关机位置: